

Using USB Camera

Using USB Camera

1. Environment Preparation

2. Execution Method

Usage instructions (default usb_pixel_format is mjpeg)

3. Expected Results

To achieve environmental awareness capabilities, robotic products typically include cameras to acquire image information. USB cameras are easy to obtain, convenient to use, and highly versatile. TogetherROS.Bot adds support for USB cameras and supports standard ROS2 image messages.

Note:

To run this section, you need to first learn the TogetherROS.Bot vision application chapter and install the TROS environment.

1. Environment Preparation

- Connect the power supply.
- Connect the USB camera to the development board and ensure that the `/dev/video8` device node is created.
- Connect the development board to the monitor using an HDMI cable.
- Log in to the RDK S100(P) via MobaXterm or other SSH tools.
- Confirm that your USB camera is working correctly and connect it to the RDK's USB slot.
- The RDK has been flashed with the Ubuntu 20.04/Ubuntu 22.04 system image.
- tros.b has been successfully installed on the RDK.
- Confirm that your PC can access the RDK via the network.

2. Execution Method

Usage instructions (default usb_pixel_format is mjpeg)

- Log in to RDK via SSH and confirm the USB camera device name (e.g., `/dev/video0`).
- Then, start the USB camera using the following command.

```
# Configure the tros.b environment
source /opt/tros/humble/setup.bash
```

```
# Launch method:
ros2 launch hobot_usb_cam hobot_usb_cam.launch.py
usb_video_device:=/dev/video0
```

- If the program outputs the following information, it means the node has started successfully.

```
[INFO] [launch]: All log files can be found below /root/.ros/log/2024-01-18-19-44-39-419588-ubuntu-3951
[INFO] [launch]: Default logging verbosity is set to INFO
[INFO] [hobot_usb_cam-1]: process started with pid [3953]
[hobot_usb_cam-1] [WARN] [1705578280.808870437] [hobot_usb_cam]: framerate: 30
[hobot_usb_cam-1] [WARN] [1705578280.809851560] [hobot_usb_cam]: pixel_format_name: mjpeg
[hobot_usb_cam-1] [WARN] [1705578280.936697507] [hobot_usb_cam]: This devices supported formats:
[hobot_usb_cam-1] [WARN] [1705578280.936858791] [hobot_usb_cam]: Motion-JPEG: 640 x 480 (30 Hz)
[hobot_usb_cam-1] [WARN] [1705578280.936912830] [hobot_usb_cam]: Motion-JPEG: 1920 x 1080 (30 Hz)
[hobot_usb_cam-1] [WARN] [1705578280.936960328] [hobot_usb_cam]: Motion-JPEG: 320 x 240 (30 Hz)
[hobot_usb_cam-1] [WARN] [1705578280.937007285] [hobot_usb_cam]: Motion-JPEG: 800 x 600 (30 Hz)
[hobot_usb_cam-1] [WARN] [1705578280.937053241] [hobot_usb_cam]: Motion-JPEG: 1280 x 720 (30 Hz)
[hobot_usb_cam-1] [WARN] [1705578280.937098906] [hobot_usb_cam]: Motion-JPEG: 1024 x 576 (30 Hz)
[hobot_usb_cam-1] [WARN] [1705578280.937144528] [hobot_usb_cam]: YUYV 4:2:2: 640 x 480 (30 Hz)
[hobot_usb_cam-1] [WARN] [1705578280.937190068] [hobot_usb_cam]: YUYV 4:2:2: 1920 x 1080 (5 Hz)
[hobot_usb_cam-1] [WARN] [1705578280.937235858] [hobot_usb_cam]: YUYV 4:2:2: 320 x 240 (30 Hz)
[hobot_usb_cam-1] [WARN] [1705578280.937282064] [hobot_usb_cam]: YUYV 4:2:2: 800 x 600 (20 Hz)
[hobot_usb_cam-1] [WARN] [1705578280.937328020] [hobot_usb_cam]: YUYV 4:2:2: 1280 x 720 (10 Hz)
[hobot_usb_cam-1] [WARN] [1705578280.937373518] [hobot_usb_cam]:
```

3. Expected Results

View the USB camera image on the web interface; open another terminal:

```
# Configure the tros.b environment
source /opt/tros/humble/setup.bash
```

```
# Start the websocket
ros2 launch websocket websocket.launch.py websocket_image_topic:=/image
websocket_only_show_image:=true
```

On your PC, open a web browser (Chrome/Firefox/Edge), enter `IP:8000` (where IP is the RDK's IP address), and click on the "Web Display" option in the upper left corner to view the live feed from the USB camera.

